



CorelDRAW[®]

TECHNICAL SUITE 2026

DEPLOYMENT GUIDE

© 2026 Corel Corporation. All rights reserved.

CorelDRAW® Technical Suite Deployment Guide

Corel, the Corel logo, Corel Balloon logo, CorelDRAW, CorelDRAW Balloon logo, CorelDRAW Go Balloon Logo, Corel DESIGNER, Corel PHOTO-PAINT, CAPTURE, Go, LiveSketch, Pointillizer, and PowerTRACE are trademarks or registered trademarks of Corel Corporation in Canada, the United States and/or elsewhere. All other company, product and service names, logos, brands and any registered or unregistered trademarks mentioned are used for identification purposes only and remain the exclusive property of their respective owners. Use of any brands, names, logos or any other information, imagery or materials pertaining to a third party does not imply endorsement. We disclaim any proprietary interest in such third-party information, imagery, materials, marks and names of others. For all notices and information about patents, please visit www.corel.com/patents.

Original sample artwork is provided by third parties and is used, and/or modified, by permission unless otherwise agreed with such parties.

Product specifications, pricing, packaging, technical support and information (“specifications”) refer to the retail English version only. The specifications for all other versions (including other language versions) may vary.

205036

Contents

Introduction.....	3
Stage 1: Preparing for deployment.....	5
Getting to know your network.....	5
Getting to know the software.....	5
Setting up your network accordingly.....	7
Stage 2: Creating the server image.....	9
Before creating a server image.....	9
Creating a basic image.....	10
Finalizing the server image.....	12
Creating a customized image.....	13
Creating multiple images.....	13
Stage 3: Installing the software.....	15
Pulling the software.....	15
Pushing the software.....	16
Specifying the setup file.....	16
Using switches.....	17
Using public properties.....	19
Running your command line.....	21
Using product privileges.....	22
Stage 4: Maintaining the installations.....	23
Repairing the software.....	23
Modifying the software.....	24
Updating the software.....	25
Removing the software.....	27
Troubleshooting the software.....	28
Appendix A: Specialized deployment scenarios.....	29
Deploying a custom set of features.....	29
Specifying software features by feature name.....	29
Deploying specific languages.....	31
Deploying XVL Studio Corel Edition and XVL Player.....	32

Understanding workspaces.....	33
Working with MSI files.....	34
Working with registry keys.....	36
Configuring content for offline availability.....	38
Customizing the setup fileset.....	39
Creating a server image with a customized fileset.....	40
Deploying customized installation settings.....	41
Appendix B: Authenticating the software.....	43
Exchanging information during authentication.....	43
Requirements for authentication.....	43
Appendix C: FAQ.....	45

CorelDRAW®

TECHNICAL SUITE 2026



Introduction

Welcome!

This Help guide provides support to administrators deploying CorelDRAW® Technical Suite to a network. The Help is also published in PDF format as the [CorelDRAW Technical Suite Deployment Guide](#).

For information about deploying the software in offline mode, see [“Deployment with Internet features off”](#) on page 12.

Contents

- [“Stage 1: Preparing for deployment”](#) (page 5)
- [“Stage 2: Creating the server image”](#) (page 9)
- [“Stage 3: Installing the software”](#) (page 15)
- [“Stage 4: Maintaining the installations”](#) (page 23)
- [“Appendix A: Specialized deployment scenarios”](#) (page 29)
- [“Appendix B: Authenticating the software”](#) (page 43)
- [“Appendix C: FAQ”](#) (page 45)

Conventions

Please note the following conventions used in this guide.

Wherever you see this

italicized text

bold monospace text

For more information

The following resources offer additional support.

For more information on

Corel Corporation, or a specific Corel software product

support for Corel software

You'll find

A placeholder for user-specified information, such as a path or filename

A reference to programming syntax

See the following resource

Corel website:
www.corel.com

Corel Support Services website:

For more information on

See the following resource

www.corel.com/support

the Microsoft Windows Installer (MSI) technology, which is used to install Corel software

Microsoft website

CorelDRAW[®]

TECHNICAL SUITE 2026



Stage 1: Preparing for deployment

Before beginning the deployment, take the time to familiarize yourself with your network and the software you want to deploy to it. Doing so can help your administrative duties run as smoothly as possible.

In this stage

- “Getting to know your network” (page 5)
- “Getting to know the software” (page 5)
- “Setting up your network accordingly” (page 7)

Highlights

- “Server requirements” (page 5)
- “Workstation requirements” (page 6)

Getting to know your network

Make sure to consider your network requirements for the deployment.

Administrative factors

Does your organization (or do you, as administrator) have any particular requirements for deploying and maintaining software?

Server factors

Does your server have any special characteristics or constraints?

Workstation factors

Do your workstations have any special characteristics or constraints?

User factors

Do your workstation users have any special workflows?

Getting to know the software

Make sure that your server and workstations are eligible for the software. If your organization uses a document-management system (DMS), make sure that it is supported by the software.

Server requirements

You can create an image of CorelDRAW Technical Suite on a server that meets the following requirements:

- Operating system with the latest service pack and critical updates: Windows Server 2022 or Windows Server 2025
- 4.39 GB of server space (for a typical installation without extra content)

The supported server operating systems support Remote Desktop Services (RDS) (previously known as Windows Terminal Server), but please note the following:

- You must use the CorelDRAW Technical Suite ISO file provided by Corel to install the software on the server.
- Corel Corporation does not provide technical support for installing third-party software included with the product.
- When you use remote desktop virtualization and deploy CorelDRAW Technical Suite on a server, note the following:
 - When you access the suite as an administrator, the security settings of your web browser on the server may not allow you to use the Welcome screen. By default, some web browsers have the Enhanced Security Configuration setting enabled. You must disable it for the Welcome screen to work normally.
 - By default, hardware acceleration is enabled. In virtualized environments, users must turn it off by disabling the **Use hardware acceleration** check box (**Tools** ▶ **Options** ▶ **Global** ▶ **General** page). Hardware acceleration can also be disabled by setting the following registry key to 0: **[HKEY_CURRENT_USER\SOFTWARE\Coreel\DESIGNER\27.0\Box Preferences\GlobalOptions GeneralTab] "GPUAcceleration"="0"**

For details on server permissions, see [“Server setup” on page 7](#).

Workstation requirements

You can install CorelDRAW Technical Suite on workstations that meet the following requirements:

- Windows 11 or Windows 10, 64-bit, with the latest updates
- OpenCL 1.2-enabled video card with 3+ GB VRAM (recommended)
- Intel Core i3/5/7/9 Generation 7 or newer or AMD Ryzen 3/5/7/9/Threadripper, EPYC
- 8 GB of RAM (16 GB RAM or higher recommended)
- 11 GB of hard-disk space for application and installation files
- Multi-touch screen, mouse or tablet
- 1280 x 720 screen resolution at 100% (96 dpi)
(1920 x 1200 or higher recommended)
- For optimal performance, ensure you have the latest device drivers provided by the manufacturer.
- Internet connection is required to install and authenticate CorelDRAW Technical Suite and access some of the included software components, online features and content.

For details on workstation permissions, see [“Workstation setup” on page 7](#).

XVL Studio Corel Edition is included and installed with CorelDRAW Technical Suite. The advanced level XVL Studio 3D CAD Corel Edition is included in CorelDRAW Technical Suite 3D CAD Edition. For processing 3D CAD assembly data we recommend:

- 8 GB RAM or more
- 1280 x 800 or higher screen resolution
- Internet connection required for product activation and installing updates

Software

CorelDRAW Technical Suite applications are available as an ISO file that you can download.



To use an ISO file, you can do one of the following:

- Mount the ISO file as a virtual drive.
- Extract the ISO file contents by using WinZip® or other third-party software.

Optionally, other content is available for download from a shared drive. This content includes images (vector files and photos), fills, fonts, and templates.

The default installation of CorelDRAW Technical Suite offers a limited number of fills and transparencies so it is important to download and install the fill packs included in the **Fills** folder.

For more information, see “Server setup” on page 7.



Note that training videos are not available for download. You can access Hints videos and other videos on the CorelDRAW and CorelDRAW Technical Suite YouTube channels, or from the Welcome screen in CorelDRAW®, Corel DESIGNER™, and Corel PHOTO-PAINT™.

For more information

For important notes on installing and using the software, it’s a good idea to review the Readme file for the software.

To access the Readme file on the installation disc

- Run the following command line (where X: is the disc drive):

```
X:\ReadMes\EN\Readme.html
```



Readme files for other languages can be accessed from their respective language folders on the DVD or the software ISO. Examples:

- **X:\ReadMes\DE\Readme.html**
- **X:\ReadMes\FR\Readme.html**
- **X:\ReadMes\JP\Readme.html**

Setting up your network accordingly

After familiarizing yourself with your network and the software you want to deploy to it, you can set up your network accordingly.

Server setup

Do the following:

- Make sure that you are either a local administrator or an administrator for the domains and workgroups that you are managing.
- Create a shared network location for the server image, and make sure that you have read/write access to that location.
- Make sure that there is internet access.

If you want to make extra content (such as clipart, photos, and fills) available to workstation users in an offline network environment, do the following:

- Set up a shared network location, and make sure that users have access to that location.
- You will receive a confirmation Proof of Entitlement Certificate email containing a URL linking to a shared drive containing the extra content, which you can download. Some of the downloadable content consists of Zip files that you must extract to the shared network location by using WinZip or another compression tool.



The extracted content is 5.75 GB.

Workstation setup

Make sure that:

- you are — and anyone else who will be installing the software is — either a local administrator or an administrator for the domains and workgroups that you are managing.
- you have — and anyone else who will be installing the software has — read access to the server-image location.

GPOs

To more easily manage the access rights of workstation users — especially for pull-installation scenarios — you may want to consider using Group Policy Objects (GPOs). For more advanced information, please refer to the Software Development Kit (SDK) for Group Policy, which is available from Microsoft.

CorelDRAW[®]

TECHNICAL SUITE 2026



Stage 2: Creating the server image

After preparing for deployment, you're ready to create the server image.

To create a basic image, you must initialize the setup. You can create a customized image by modifying the settings in the setup UI. If you want to support multiple installation types, you can create multiple server images.

In this stage

- "Before creating a server image" (page 9)
- "Creating a basic image" (page 10)
- "Finalizing the server image" (page 12)
- "Creating a customized image" (page 13)
- "Creating multiple images" (page 13)

Before creating a server image

corel.com account

You must have a corel.com account before running the administrative installation. If you don't have a corel.com account, go to coreldraw.com, and click **Sign in** (upper-right of page), then click **My account**. On the sign-in page, enter your email address, click **Continue** and follow the steps to create an account.



When creating a corel.com account, validate the email that is sent to the email address you used to create the account to avoid service disruption.

The account credentials (email address and password) used when first signing in to create a server image are the only account credentials that will be recognized for future sign-ins. Make note of the first credentials used.

It is recommended that you use an IT department email address as corel.com account name.

Customers will receive a Proof of Entitlement Certificate email, which serves as proof of purchase. It contains instructions for importing subscription or perpetual licenses into the corel.com customer account. Optionally for perpetual licenses, it also provides direct access to the software download and serial numbers.

Offline and online mode

In some corporate environments, users must use the software in offline mode, without access to product features that require Internet connection and product authentication. Internet features include:

- access to videos and other online content from the Welcome screen and from the **Explore** tab of the **Learn** docker in CorelDRAW and Corel PHOTO-PAINT
- in-product purchases from the Welcome screen or other access points in the software

- AI image generation
- AI-assisted background removal
- QR codes
- online Help
- access to Corel Cloud

To restrict access to Internet features and product updates, you need a special serial number to create the server image. This setup will deploy the software to the workstations in offline mode. For more information, see [“Deployment with Internet features off” on page 12](#). When access to Internet features is restricted, you can still allow users to save files in the Corel Cloud. For more information, see [“ALLOW_CORPORATECLOUDFEATURES” on page 19](#).

In online mode, workstation users have access to all Internet features as well as product updates.

Saving files in the Corel Cloud

To access collaboration features such as the **Comments** docker and save files to the cloud, users must sign in to Corel Cloud.

Sign-in to Corel Cloud

The first time users access Corel Cloud from CorelDRAW, they are prompted to sign in to Corel Cloud with the email and password associated with your Corel account.

Creating a basic image

To create a basic server image, you must initialize the setup. After setting up the image and tweaking it as necessary, you can use it for deployment.

Initializing the setup

- To initialize the setup for creating a server image, you can use a command line.



The following command line lets you initialize the full Setup UI and create a basic 64-bit server image:

- **X:\x64\Setup.exe /a**



If you want to create a log file of installation events, include the **/L** switch in your command line. For details on this switch, see [“/L - Event logging” on page 17](#).

Setting up the server image

If your **/a** command line succeeds, the setup initializes in one of two ways:

- with full UI and Internet features on — This is the default deployment option, which allows the workstations to work in online mode. Internet features are enabled and can't be turned off.
- with full UI and Internet features off — requires a special serial number and allows the workstations to work in offline mode



You can no longer use the **/q (n)** switch for creating a server image with limited setup UI.

The **Share feature usage** feature on Windows is internet-based. When internet features are enabled, Corel tracks feature usage and uses this information to improve the applications.

Full setup UI

The setup UI takes you step-by-step through the process of setting up the server image.

UI component

Business User License Agreement (BULA)

Serial number, email address and password

For perpetual licenses, the Proof of Entitlement Certificate email contains the required serial number, which is assigned to the corel.com account used when creating the server image.

Subscription licenses require a license import, which is described on the license certificate.

For more information, see [“Before creating a server image” on page 9](#).

ProfileID

Image Location

Deploy with internet features on

Product Updates

Welcome screen

Notes

To create the server image, you must accept — on behalf of your organization — the Business User License Agreement. Installations deployed from the image will not prompt users to review the license agreement.

A valid serial number and your corel.com account information, such as email address and password, are required to create the server image and access internet-based features and product updates.

The ProfileID may be required to create the server image.

To access your ProfileID, log in to your [corel.com customer account](#). The ProfileID is displayed in the bottom-right corner.

Type the full (UNC) path in the box provided, or click **Change** to browse to that location. To prevent installation problems, limit the path to 89 characters.

This default deployment option is configured with internet features automatically enabled. Users at the workstations can access internet-based features such as QR codes, share feature usage , and online Help.

To install with Internet features off, you need a special serial number. For more information, see [“Deployment with Internet features off” on page 12](#).

You can choose to:

- automatically update the product
- check for updates and let the user choose when to install them
- never check for updates.

You can access these options only after entering the corel.com account user credentials.

You can choose to allow workstations to access the Welcome screen in offline or online mode.

When the Welcome screen is in offline mode, users cannot download and purchase items, nor can they access videos and other online content.

UI component

Notes

Allow access to generative AI-powered features

Enable this check box to allow corporate users to access AI-powered features, such as AI-generated images and AI-assisted background removal.

Users must be 18 years of age to use generative-AI features. In academic environments, admins can disable the **Allow access to generative AI-powered features** check box to deny access to students under 18 years of age.

Enable saving to Corel Cloud for corporate users

Enable this check box to allow corporate users access to the **Comments** docker and Corel Cloud. For information about using a property to accomplish this task, see ["ALLOW_CORPORATECLOUDFEATURES" on page 19](#).

For more information about the available sign-in options, see ["Saving files in the Corel Cloud" on page 10](#).

You must be online when creating the server image so that you can authenticate your profile. When you enter the email address and password associated with your corel.com account when online, a ProfileID is generated that allows users to be signed in automatically.

Deployment with Internet features off

To create a server image that allows the workstations to work in offline mode (with Internet features off), you must use a special serial number that begins with the prefix DE27CKV. Request this special serial number by sending an email to offlinedeploy@mysupport.corel.com. Make sure that the email includes the following information:

- your Corel license order number (included in the license order confirmation email)
- your CorelDRAW product serial number ("license key" as included in the license order confirmation email)
- your Corel customer account user name (email address)

The full setup UI for creating a server image with Internet features off includes all components listed in ["Full setup UI" on page 10](#), except for **Deploy with internet features on**. There is an additional UI component — **Internet features**. It is disabled by default, but you can enable it.

Finalizing the server image

This section describes recommended steps to take before deploying from the server image.



Optionally, you can finalize the image in the following ways:

- Customize the registry settings you want to deploy (see ["Working with registry keys" on page 36](#)).
- Customize the setup fileset (see ["Customizing the setup fileset" on page 39](#)).



To avoid deploying the software twice, you may want to check for software updates and apply them to the image as necessary. For details, see ["Updating the software" on page 25](#).

Testing the image

You may want to test your finalized image with a small subset of workstations before rolling it out to your entire organization.

Moving the image

To change the location of a server image after you create it, you can copy the image to a new location. However, after the software has been deployed to the workstations, the image cannot be moved.

Creating a customized image

If you require a more customized server image than offered by command-line switches (see [“Using switches” on page 17](#)) and public properties (see [“Using public properties” on page 19](#)), you may want to consider the specialized scenarios discussed in [“Appendix A: Specialized deployment scenarios” on page 29](#).

Registry keys

You can edit the registry settings for the server image. See [“Working with registry keys” on page 36](#).

Setup fileset

You can customize the setup fileset. See [“Customizing the setup fileset” on page 39](#).

Installation settings

You can customize the settings used to install the software on the workstations. See [“Deploying customized installation settings” on page 41](#).

Creating multiple images

If your workstations require different configurations of the software, you can create one server image for each installation type.

Product updates

When a product update becomes available, you will need to apply it to each server image. For details on image patching, see [“Image patching” on page 25](#).

Naming convention

Use a naming convention that makes it easy to distinguish the server images from one other.

CorelDRAW[®]

TECHNICAL SUITE 2026



Stage 3: Installing the software

After creating the server image, you can use it to install the software on the workstations in one of two ways:

- manually, by having users “pull” the software to their own workstations
- automatically, by “pushing” the software to the workstations on their users’ behalf

In this section

- [“Pulling the software” \(page 15\)](#)
- [“Pushing the software” \(page 16\)](#)
- [“Specifying the setup file” \(page 16\)](#)
- [“Using switches” \(page 17\)](#)
- [“Using public properties” \(page 19\)](#)
- [“Running your command line” \(page 21\)](#)
- [“Using product privileges” \(page 22\)](#)

Pulling the software

If users have both access to the server and administrator-level rights to their workstations, they can install (or “pull”) the software themselves. To do this, they run the setup from the server image.

Preparing for pull installation

To ensure that the pull-installation process runs as smoothly as possible, take the time to prepare for it.

Requirements

- Confirm that each workstation meets the minimum requirements for the software (see [“Workstation requirements” on page 6](#)).
- Confirm that each workstation user has read-only access to the server image and administrator-level access to the workstation (see also [“Workstation setup” on page 7](#)).

Recommendation

Map the workstations to the server image, and set the workstations to log in to that server location at startup. Doing so ensures that users are always connected to the server image.

Carrying out a pull installation

Users pull the software to their workstations by running the setup from the server image.



The degree of user interaction required by the setup depends on how you've customized the server image and the deployment process.



If you prefer to restrict user customization, you may want to offer multiple server images — one per set of installation options. For details, see ["Stage 3: Installing the software" on page 15](#).

To pull the software to a workstation

- 1 Browse to the location of the server image, and double-click **Setup.exe**.
- 2 Carry out the installation, specifying any desired options, by following the on-screen instructions.



To prevent installation problems, limit the installation path to 50 characters.

Pushing the software

To "push" the software from the server image to the workstations, you must write a command line that includes the following:

- the filename of the setup you want to use
- any desired switches, to control how the setup runs
- any desired public properties, to specify installation settings

Example: **Setup.exe /q**

Using this command line, you can install the software on the workstations by using any supported push method.



When pushing a server image to workstations, the setup must be run with administrator-level privileges.



If the **Security level for this zone** setting is set to **High** in the **Internet Properties** dialog box (**Windows Control Panel** ► **Internet Options** ► **Security tab**), no text will appear in the CorelDRAW Technical Suite installation dialog boxes. You can modify this setting so that text will appear by following the procedure below.

To modify security settings for web browsers

- 1 On the Windows Control Panel, click **Network and Internet**.
- 2 Click **Internet Options**.
- 3 Click the **Security** tab.
- 4 Click the **Custom level** button.
- 5 In the **Scripting** list of options, enable the **Enable** option for **Active scripting**.
- 6 Click **OK**, and click **OK** again.

Specifying the setup file

The most important item to specify in your command line is the executable file for the setup: the Setup.exe file on the server image you want to use:

- `\\server\path\Setup.exe`
- `\\server\path\x64\Setup.exe` — to push the 64-bit version of the software to 64-bit operating systems



If your path contains spaces, you must place quotation marks around it:

- `"\\server\path containing spaces\Setup.exe"`

Using switches

By using switches in your command line, you can control the setup process. Listed in this section are the switches most commonly used when installing the software.

For a list of all command-line switches for Microsoft Windows Installer, please see the Microsoft website.

/L - Event logging

Use `/L` to log installation events.

Parameter	What it logs
<code>i</code>	Status messages
<code>w</code>	Nonfatal warnings
<code>e</code>	All error messages
<code>a</code>	Initiated actions
<code>r</code>	Action-specific records
<code>u</code>	User requests
<code>m</code>	Error messages for out-of-memory warnings or fatal exits
<code>o</code>	Error messages for insufficient hard-disk space during server installation
<code>p</code>	Terminal properties
<code>*</code>	All of the above, in a single log file NOTE: Alternatively to <code>/L*</code> , you can use <code>/log</code> .
<code>v</code>	Very detailed information

The default parameters for `/L` are `iwearmo`.

If you want to specify a path for the log file, use the following syntax:

```
/L "C:\Logs\My_Log.txt"
```



If you do not specify a path and filename, the log file is created in the current user's temporary (**Temp**) folder.

In the following example, the **/L** switch (with default parameters) is used to log installation events in the specified file:

```
\\server\path\Setup.exe /L "C:\Logs\My_Log.txt"
```

/q - Push the server image to the workstations

You can use **/q** to push the software to the workstations.

You can use **/q** to prevent users from entering their own registration information, to help enforce specific installation options, or even to perform silent installations (in which no setup UI is visible whatsoever).

Parameter	What the user sees during installation
n	No UI whatsoever. Errors are logged in a file that you can control by using /L (see " /L - Event logging " on page 17). This is the default parameter. NOTE: Alternatively to /qn , you can use /quiet .
b	Basic UI: a progress bar and a Cancel button. If the user pushes the Cancel button, the installation is rolled back upon confirmation. NOTE: Alternatively to /qb , you can use /passive .
b!	Basic UI: only a progress bar. The user cannot cancel the installation.
b+	Basic UI: a progress bar and a Cancel button. If the user pushes the Cancel button, the installation is rolled back (without first prompting for confirmation).
r	Reduced UI: A progress bar, along with a page containing information about the installation. The user can cancel the installation. Note: When run on a workstation, a command line with this parameter automatically installs any needed components.
f	Full UI

The default parameter for **/q** is **n**.

In the following example, all setup UI is suppressed, and any errors are recorded in the specified log file:

```
\\server\path\Setup.exe /q /L "C:\Logs\My_Log.txt"
```

/? - Help

The **/?** switch (or **/help**) displays Help for the setup.

Using public properties

By using public properties in your command line, you can specify installation settings. Listed alphabetically in this section are the properties most commonly used during software installation.

For a list of all command-line properties for Microsoft Windows Installer, please see the Microsoft website.

ADDLOCAL

Installing specific components

For details on this scenario, see the following topics in the appendix:

- “Deploying a custom set of features” (page 29)
- “Deploying specific languages” (page 31)

ALLOW_CORPORATECLOUDFEATURES

Specifying settings for cloud storage features

The **ALLOW_CORPORATECLOUDFEATURES** property allows users to sign in to the **Comments** docker, use the **Save to Cloud** feature, and open files from the Cloud even when Internet features are turned off. For example, users can add comments to files and upload the files to Corel Cloud for storing and accessing the files from any device. Users can also sign in to the Cloud from the **Assets** docker to view and link Cloud assets.

You can allow access to cloud storage features by using the following property:

```
ALLOW_CORPORATECLOUDFEATURES=1
```

If this property is not specified, cloud storage features are turned on, and users can save files to Corel Cloud, and use the **Comments** docker.

You can restrict access to the Cloud by using the following property:

```
ALLOW_CORPORATECLOUDFEATURES=0
```



Cloud storage features can't be turned on or off after installation.

ALLOW_PRODUCTUPDATES

Specifying settings for product updates

You can check for updates and let the user choose when to install by using the following property:

```
ALLOW_PRODUCTUPDATES=0
```

You can keep the product automatically updated (and allow in-product messaging) by using the following property:

```
ALLOW_PRODUCTUPDATES=1
```

You can opt out of automatic updates (and in-product messaging) by using the following property:

```
ALLOW_PRODUCTUPDATES=2
```



There are default settings for product updates based on whether the administrator signs in with credentials.

If the administrator does not sign in, **ALLOW_PRODUCTUPDATES=2** is the default, and cannot be modified later.

If the administrator enters credentials before creating the basic server image or specifies a ProfileID at the command line, **ALLOW_PRODUCTUPDATES=1** is the default, but can be modified later.

DESKTOPSHORTCUTS

Specifying settings for desktop shortcuts

You can prevent the installation of desktop shortcuts by using the following property:

DESKTOPSHORTCUTS=0

You can allow the installation of desktop shortcuts by using the following property:

DESKTOPSHORTCUTS=1



If nothing is specified, **DESKTOPSHORTCUTS=1** is the default.

GENAIFEATURES

Allow access to generative AI-powered features

The **GENAIFEATURES** property allows you to give users access to AI-powered features, such as AI-image generation and AI-assisted background removal.

You can allow access to AI-powered features by using the following property:

GENAIFEATURES=1

You can restrict access to AI-powered features by using the following property:

GENAIFEATURES=0



Users must be 18 years of age to use generative-AI features. In academic environments, admins can use the **GENAIFEATURES** property deny access to students under 18 years of age.

INSTALLDIR

Customizing the installation path

When deploying from the server image, use the following public property to customize the workstation installation path of the software:

INSTALLDIR="path"

This property can only be used during a workstation installation.



For best results, do not end the path with a backslash (\).

REBOOT

Handling reboots

The **REBOOT** property is used with one of the following values to specify how the installation process handles any required reboots.

Value	What it does
Force (or F)	Prompts for reboot after installation. If the setup UI is suppressed, the computer is automatically rebooted after installation. NOTE: Alternatively to REBOOT=Force , you can use the / forcerestart switch.
Suppress (or S)	Prompts for reboot during installation (if required), but reboots automatically after installation. If the setup UI is suppressed, all required reboots are automatic.

Value	What it does
ReallySuppress (or R)	<p>NOTE: Alternatively to REBOOT=Suppress, you can use the /promptrestart switch.</p> <p>Suppresses all reboots and all reboot prompts, both during and after installation.</p> <p>NOTE: Alternatively to REBOOT=ReallySuppress, you can use the /norestart switch.</p>

SERIALNUMBER

Specifying the serial number

The **SERIALNUMBER** property is used to specify the serial number for the installation:

```
SERIALNUMBER=<SerialNumber>
```

TARGETDIR

Specifying the location of the server image

The **TARGETDIR** property is used to specify the desired location of the server image.

```
TARGETDIR=<PathToAdminImage>
```

This property can only be used during server image installations.



For best results, do not end the path with a backslash (\).

WELCOMESCREENONLINE

Setting the Welcome screen in offline or online mode

This property lets you set the Welcome screen in offline or online mode. When the Welcome screen is in offline mode, users cannot download and purchase items. To set the Welcome screen in offline mode, use the following syntax:

```
WELCOMESCREENONLINE=off
```

If **WELCOMESCREENONLINE** is not set to **off** or is any other value different from **off**, the Welcome screen is in online mode. Users can download and purchase items.



If the administrator deploys the software offline, this property is irrelevant for the workstation installations.

WELCOMESCREENONLINE is automatically set to **off**.

You can change the value of **WELCOMESCREENONLINE** in the **Persist.xml** file, stored at the root of the server image. For more information about customizing the installation settings, see [“Deploying customized installation settings” on page 41](#).

Running your command line

Your command line can be used to push the software to the workstations through any of the following:

- a **batch file** — see the Microsoft website for details
- a **GPO** — see the Group Policy SDK for details
- a **third-party push technology** — see the manufacturer’s documentation for details

For many administrators, using a third-party push technology is the preferred push method. This section offers general guidelines on using a few such technologies. For details on using such a technology, please refer to the manufacturer's documentation.

SCCM

At the time of this writing, Corel has verified support for Microsoft System Center Configuration Manager (SCCM) only insofar as its Microsoft Systems Management Server (SMS) components.

For complete information on using SCCM, please see the Microsoft website.

SMS

For deployment to the workstations on a "per-system" basis using package definition files (or "packages"), CorelDRAW Technical Suite supports the use of Microsoft Systems Management Server (SMS).

You can create a package from scratch — or you can create one from the existing SMS files included with CorelDRAW Technical Suite (in the **Administrator** folder on the installation disc or the server image).

For complete information on using SMS files, please refer to your resource kit for Microsoft Systems Management Server.



The recommendations posted on the Microsoft website have not been tested with CorelDRAW Technical Suite and must therefore be used at your discretion.

Using product privileges

To take advantage of product privileges, such as silent updates, after deployment, workstations must have internet access the first time they launch the applications. Users can then work offline, but they won't have access to internet-based features.



For successful software authentication on a corporate network, allow access to <https://iws.corel.com>, the address of the Corel authentication server. Use port 443, with the following endpoint: <https://iws.corel.com>. If the sign-in dialog appears, ensure access to <https://ipm.corel.com>, <https://idp.coreldraw.com>, <https://wll741ba4c.execute-api.us-east-1.amazonaws.com/prod/getautheninfo>, and <https://myaccount.corel.com> for authentication.

Users can be automatically signed in to the corel.com account associated with your volume license purchase provided you included your corel.com account credentials (email address and password) during the creation of the server image. Users can also sign in themselves at the first application launch after installation if you have invited them to authenticate their license with their personal corel.com account. This ensures that they can use their product privileges.

You can choose to remove specific workstations from your [My account](#) page on corel.com. To sign in workstations that you previously signed out, you must provide account credentials.



For detailed information about license management options for CorelDRAW Technical Suite, please visit the [CorelDRAW Learning Center](#) and consult the [Corel Knowledgebase](#).

CorelDRAW®

TECHNICAL SUITE 2026



Stage 4: Maintaining the installations

An important part of administering a network is maintaining the software installed on its workstations.

In this stage

- “Repairing the software” (page 23)
- “Modifying the software” (page 24)
- “Updating the software” (page 25)
- “Removing the software” (page 27)
- “Troubleshooting the software” (page 28)

Repairing the software

Repairing the software lets you install (or reinstall) missing (or corrupted) components. You can repair a single installation of the software by using the Windows Control Panel on that workstation, or you can repair multiple workstation installations by using a command line.

Repairing a single installation

You can use the Windows Control Panel to repair a single installation.

Repairing multiple installations

You can use a command line to repair multiple installations at a time.

To repair an installation with the Windows Control Panel

- 1 In the Windows Control Panel, display the list of currently installed programs, and choose the program from the list.
- 2 Click **Uninstall/Change**.
- 3 Enable the **Repair** option, and then click **Repair**.
- 4 Follow the on-screen instructions.

To repair multiple installations with /f switch

- Use the **/f** switch with the Setup.exe file on the server image:

```
\\server\path\Setup.exe /f
```



You cannot use the **/f** switch with public properties. For greater control over the repair process, use the **REINSTALL** and **REINSTALLMODE** properties instead of **/f**.

The **/f** switch has the following parameters.

Parameter	What it does
p	Reinstalls missing files
o	Reinstalls missing files and files older than current version
e	Reinstalls missing files and files equal to or older than current version
d	Reinstalls missing files and files different from current version
a	Reinstalls all files
u	Reinstalls all required user-specific registry keys: HKEY_CURRENT_USER, HKEY_USERS
m	Reinstalls all required computer-specific registry keys: HKEY_LOCAL_MACHINE, HKEY_CLASSES_ROOT
s	Reinstalls all existing shortcuts
v	Runs from the source files and re-caches the local package

The default parameters for **/f** are **oums**.

Advanced repair

For greater control over how the software is repaired, use the **REINSTALL** and **REINSTALLMODE** public properties together.

Property	What it does
REINSTALL=ALL	Reinstalls all program features. If you prefer to reinstall only specific features (see “Deploying a custom set of features” on page 29 for a list), use the following syntax: REINSTALL=Feature
REINSTALLMODE=type	Specifies the type of reinstallation to perform. The values for this property are the same as the parameters for the /f switch, so its default values are oums .

Modifying the software

Modifying the software lets you change which program features are installed. You can modify a single installation of the software by using the Windows Control Panel on that workstation, or you can modify multiple workstation installations by using a command line.

Modifying a single installation

You can use the Windows Control Panel to modify a single installation.

Modifying multiple installations

You can use a command line to add features to or remove features from multiple installations at a time.

To modify an installation with the Windows Control Panel

- 1 In the Windows Control Panel, display the list of currently installed programs, and choose the program from the list.
- 2 Click **Uninstall/Change**.
- 3 Enable the **Modify** option, and then click **Next**.
- 4 Follow the instructions that appear.

To modify multiple installations

Adding features

You can use the **ADDLOCAL** public property to add program features:

```
ADDLOCAL=Feature
```

For more than one feature, use a comma-separated list, with no spaces between the comma and the feature name:

```
ADDLOCAL=Feature1,Feature2
```

For a list of available features, see [“Deploying a custom set of features” on page 29](#).

Removing features

You can use the **REMOVE** public property to remove a program feature:

```
REMOVE=Feature
```

For more than one feature, use a comma-separated list, with no spaces between the comma and the feature name:

```
REMOVE=Feature1,Feature2
```

For a list of available features, see [“Deploying a custom set of features” on page 29](#).

If you want to add nearly all features and remove only a couple of features, you can use the **ADDLOCAL** public property in conjunction with the **REMOVE** public property. For more information, see [“Deploying a custom set of features” on page 29](#).

Application languages are considered as features as well. You can use the **ADDLOCAL** public property and the **REMOVE** public property to add and remove application languages. For more information, see [“Deploying specific languages” on page 31](#).

Updating the software

Corel periodically releases Microsoft patch (MSP) files — also known as “patches” or “updates” — for its products. Installing updates helps keep the software up-to-date.



In this guide, `Patch.exe` is a placeholder for the filename of the update. The actual filename varies with each update.

Image patching

You can apply an update to the server image. You must begin by extracting the patch files to a specified location.

Locating updates

Many network administrators keep their software up-to-date by monitoring the Corel Support Services website (www.corel.com/support). When an update is made available, these administrators download it and carry out the patching process themselves.



In this guide, `\\server\path\Patch.exe` is a placeholder for the location and filename of the downloaded patch.



If you prefer to have workstation users patch the software for themselves, you can set up the server image to enable the automatic detection of available patches. For details, see [“Setting up the server image” on page 10](#).

Applying updates

After locating and downloading an update, you can apply it to the server image and then use the updated image to patch the installed software.

Workstation patching

After updating the server image, you can deploy the update to the workstations.



Corel will provide patches for any updates to XVL Studio Corel Edition and XVL Player, which are included with CorelDRAW Technical Suite. However, the process of applying a XVL Studio Corel Edition patch to the server image may differ from the process described here. For guidance, please refer to the patch notes. For more information, see [“Deploying XVL Studio Corel Edition and XVL Player” on page 32](#).

To extract the patch to a specified location

- To extract the patch to a specified location (instead of the default **Temp** folder), use the following command-line syntax:

```
\\server\path\Patch.exe /extract_all "C:\Extracted"
```



After extracting the patch, be sure to apply all extracted patch files to the server image. Applying only some of the patch files may cause the installations to function incorrectly.

To apply the extracted patch files to the server image

- Use a command line that includes the executable file for the patch and the **/a** switch. For example, if the patch was extracted to **c:\Extracted**, the command line will look like this:

```
C:\Extracted\Setup.exe /a
```

To update the workstations

- Use the following command-line syntax:

```
\\server\path\Setup.exe REINSTALL=ALL
```



By default, the **REINSTALLMODE=oums** property is applied. For best results, you may want to specify **REINSTALLMODE=vdm**:

- `\\server\path\Setup.exe REINSTALL=ALL REINSTALLMODE=vdm`

For details on **REINSTALL** (and **REINSTALLMODE**), see [“Advanced repair” on page 24](#).

To silently update the workstations

- Use the following command line:

```
\\server\path\Setup.exe REINSTALL=ALL REINSTALLMODE=vdm /qn
```

Removing the software

You can remove the software from your network. Uninstalling the software cleanly is crucial when the time comes to upgrade to a newer version.

Image removal

You cannot automate the removal of a server image. Instead, you must manually delete the image from the server.

For best results with deleting an image, make sure that the programs to be removed — and their associated files — are not currently in use on the workstations.



The only way to recover a deleted server image is to re-create it by re-running the setup.

Don't delete the server image if there are still workstations that use the image. Otherwise, users won't be able to maintain and modify the installations.

Removing the software from a server

If Remote Desktop Services (formerly known as Windows Terminal Server) are used so that users can run the applications from a server, make sure that all users are logged off before you remove the software.

Removing a single installation

You can use the Windows Control Panel to remove a single installation.

Removing multiple installations

You can use a command line to remove multiple installations at a time.

Removing VBA

Visual Basics for Applications (VBA) is not uninstalled when the software is removed. VBA must be uninstalled separately.

To remove an installation with the Windows Control Panel

- 1 In the Windows Control Panel, display the list of currently installed programs, and choose the program from the list.
- 2 Click **Uninstall/Change**.
- 3 Enable the **Remove** option.
- 4 If you want to remove user files (such as presets, user-created fills, and customized files), enable the **Remove user files** check box.
- 5 Click **Remove**.

Repeat for **Corel Graphics - Window Shell Extension** and **Ghostscript GPL**.

To remove multiple installations with the /x switch

- You can use the **/x** switch (or the **/uninstall** switch) to silently remove the software:

```
\\server\path\Setup.exe /x
```

When you remove CorelDRAW Technical Suite, XVL Studio Corel Edition and XVL Player are removed by default. If you want to silently remove CorelDRAW Technical Suite but not XVL Studio Corel Edition and XVL Player, use the following syntax:

```
\\server\path\Setup.exe /x /qb DO_NOT_REMOVE_XVL=1
```



You must use the **b** parameter with the **q** switch (**/qb**). Using either the **n** (**/qn**) or **r** parameter (**/qr**) will not work.

Advanced removal

If you want more control over the removal process, use the **REMOVE** and **REMOVEUSERFILES** public properties.

Property	What it does
REMOVE=ALL	Removes all features (except GPL Ghostscript and Windows Shell Extension)
REMOVEUSERFILES=value	Specifies whether to remove user files: <ul style="list-style-type: none">• 0 — no• 1 — yes
REMOVE_GPL=1	Removes GPL Ghostscript
REMOVE_SHELLEXT=1	Removes Windows Shell Extension

For example, if you want to uninstall both GPL Ghostscript and Windows Shell Extension, you can use the following command:

```
\\server\path\Setup.exe /x REMOVE_SHELLEXT=1 REMOVE_GPL=1
```

To uninstall VBA

- 1 In the **Start** menu, type **Run**, and press **Enter**.
- 2 In the **Run** dialog box, type **regedit**, press **Enter**.
- 3 In the **Registry Editor**, note the VBA GUIDs in the following registry hive:
Computer\HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall
- 4 In the **Start** menu, type **cmd**, and press **Enter**.
- 5 Run the following command line (where **{GUID_CODE}** is a VBA GUID noted in step 3):
MsiExec.exe /x {GUID_CODE}
- 6 Click **Yes**.

You must do this for the main VBA MSI file and each of the installed language packs.

Troubleshooting the software

For help troubleshooting any issues with the software, please visit the Corel® Knowledge Base (www.corel.com/knowledgebase), an online repository of FAQs and articles.

CorelDRAW[®]

TECHNICAL SUITE 2026



Appendix A: Specialized deployment scenarios

If you require a more specialized deployment scenario, the supplementary topics in this appendix may be of interest to you.

In this appendix

- “Deploying a custom set of features” (page 29)
- “Deploying specific languages” (page 31)
- “Working with MSI files” (page 34)

Deploying a custom set of features

When performing a basic or silent installation with the **/q** switch (see “/q - Push the server image to the workstations” on page 18), you may want to use the **ADDLOCAL** property together with the **REMOVE** property to specify a custom set of features to install. First, you use **ADDLOCAL** to include all features, and then you use **REMOVE** to specify which features you want to exclude.

```
ADDLOCAL=ALL REMOVE=Feature1,Feature2
```

For example, if you want to install all CorelDRAW Technical Suite features except Corel PHOTO-PAINT and CAPTURE™, use the following properties in the command line:

```
ADDLOCAL=ALL REMOVE=PP,Capture
```

You can specify a single feature, or a comma-separated list of components as shown in the following examples. However, we don't recommend this method because it is tedious and error-prone; you may inadvertently exclude features that you want to install.

```
ADDLOCAL=Feature
```

```
ADDLOCAL=Feature1,Feature2
```



Feature names are case-sensitive.

Specifying software features by feature name

CorelDRAW Technical Suite components are organized into the following child features of **MainApp**.

Software component	“MainApp” child feature
--------------------	-------------------------

Corel DESIGNER™	Designer
-----------------	-----------------

Software component	“MainApp” child feature
CorelDRAW	Draw
Corel PHOTO-PAINT	PP
CAPTURE	Capture
XVL Studio Corel Edition	STUDIO
XVL Player	PLAYER
Corel® Font Manager	FontManager
Utilities	Utility
Import/export filters	Filter



Some editions of the software do not include certain features listed in this section.



When you specify a parent feature (such as **MainApp**) for programs other than Corel DESIGNER, only program files are included. To add other child features, you must specify them individually. And remember: Feature names are case-sensitive.

Utilities

The utilities (feature name **Utility**) include the following child features.

Utility	“Utility” child feature
Duplex wizard (for two-sided print jobs)	DupWiz
Visual Basic for Applications (VBA)	VBAFiles



Specifying **Utility** does not include its child features. You must individually specify each desired utility.

Windows Shell Extension cannot be added or excluded by specifying the child feature name when using the **ADDLOCAL** public property. To exclude Windows Shell Extension, you must delete the following Dbm nodes from **setup.xml**:

- the node that references **ShellExt.msi**
- the node that references **64BitKey.msi**

User guides

The [Corel DESIGNER User Guide](#), [CorelDRAW User Guide](#) and the [Corel PHOTO-PAINT User Guide](#) contain comprehensive information about product features and tools. They are PDF versions of the Help that are available online and can be accessed from the Help Home pages ([Help](#) ► [Product Help](#)).

Other learning resources

In CorelDRAW and Corel PHOTO-PAINT, short **Hints** are available on the **Hints** tab of the **Learn** docker. In addition, the **Learn** docker features an **Explore** tab, which lets users search for available tools and online tutorials. However, the **Explore** tab of the **Learn** docker is automatically disabled when the server image is created so it is unavailable in network installations.

Deploying specific languages

When performing a basic or silent installation with the `/q` switch (see “[/q - Push the server image to the workstations](#)” on page 18), you may want to use the **ADDLOCAL** property to specify which software languages to support. You can specify a single language:

```
ADDLOCAL=Feature1 ,LanguageCode
```

Or you can specify a comma-separated list of languages:

```
ADDLOCAL=Feature1 ,LanguageCode1 ,LanguageCode2
```

Using language codes, you can specify language modules.



If you use the **ADDLOCAL** property in your command line to specify only languages, you will exclude all other product features. Consider using the **ADDLOCAL** property together with **REMOVE** to install all features and exclude specific languages:

```
ADDLOCAL=ALL REMOVE=LanguageCode1 ,LanguageCode2
```

Language codes are case-sensitive.

Specifying UI modules by language code

A language module includes the software UI. By installing multiple language modules, you can enable *dynamic language switching* — the ability to change the language of the software UI.

XVL Studio Corel Edition and XVL Player support only German (**DE**), English (**EN**), French (**FR**), and Japanese (**JP**).

The following table lists the available language modules for the software, along with their corresponding language codes.

Language module	Language code
Brazilian Portuguese	BR
Chinese (Simplified)	CS
Chinese (Traditional)	CT
Czech	CZ
Dutch	NL

Language module	Language code
English	EN
French	FR
German	DE
Italian	IT
Japanese	JP
Polish	PL
Russian	RU
Spanish	ES
Swedish	SV
Turkish	TR



By default, writing tools are automatically installed for all available languages.

Deploying XVL Studio Corel Edition and XVL Player

A typical server image of CorelDRAW Technical Suite includes the files required to deploy XVL Studio Corel Edition and XVL Player to the workstations.

Updating

Corel Corporation will provide patches for any updates to XVL Studio Corel Edition and XVL Player, which are included with CorelDRAW Technical Suite. Any such patches will update the server image of CorelDRAW Technical Suite with the latest files for XVL Studio Corel Edition and XVL Player. The updated software can then be deployed to the workstations by manually repairing the installed software.

Removing

XVL Studio Corel Edition can be removed by using the **XVL Studio Corel Edition** entry in the **Add or remove programs** dialog box of the Windows Control Panel.

XVL Player can be removed by using the **XVL Player / Lattice3D Player Pro (Version 9 or later)** entry in the **Add or remove programs** dialog box of the Windows Control Panel.

If you want to silently remove CorelDRAW Technical Suite but not XVL Studio Corel Edition and XVL Player, you must use the following command line:

```
Setup.exe /x /qb DO_NOT_REMOVE_XVL=1
```

Understanding workspaces

The software installs a selection of workspaces for use in Corel DESIGNER, CorelDRAW and Corel PHOTO-PAINT.

Installed Corel DESIGNER workspaces

The default workspace of Corel DESIGNER is designed to provide a more intuitive placement of tools and controls. The default settings are included in `DrawUi.xml`, which is located in the `CorelDRAW Technical Suite\27\Designer\UIConfig` folder. In addition, the following workspaces for Corel DESIGNER are installed in `CorelDRAW Technical Suite\27\Designer\Workspace`:

- `lite.cdws` — ideal for new users who are getting started
- `Micrografx Designer.cdws` — ideal for users who prefer the look and feel of Micrografx Designer 9
- `Default(TM).cdws` — has a streamlined user interface (UI) that displays only the tools and commands that users are most likely to use when using a tablet
- `Technical Illustration.cdws` — optimized for users who create technical manuals and catalogs of interactive parts
- `Diagramming.cdws` — features tools and a layout that are essential for creating diagram
- `CorelDRAW X7.cdws` — designed to help users transition easily from CorelDRAW to Corel DESIGNER
- `Adobe Illustrator.cdws` — simulates the Adobe Illustrator workspace by positioning the Corel DESIGNER features where you would find the equivalent feature in Adobe Illustrator

Installed CorelDRAW workspaces

The default workspace of CorelDRAW is designed to provide a more intuitive placement of tools and controls. The default settings are included in `DrawUI.xml`, which is located in the `CorelDRAW Technical Suite\27\Draw\UIConfig` folder.

In addition, the following workspaces for CorelDRAW are installed in `CorelDRAW Technical Suite\27\Draw\Workspace`:

- `illustration.cdws` — designed for creating book cover designs, magazine adds, storyboards, and other types of illustration
- `illustrator.cdws` — designed for Adobe Illustrator users
- `lite.cdws` — ideal for new users who are getting started
- `pagelayout.cdws` — optimized for users who are creating layouts for business cards, branding materials, product packaging, or multipage documents
- `Default(TM).cdws` — has a streamlined user interface (UI) that displays only the tools and commands that users are most likely to use when using a tablet

Installed Corel PHOTO-PAINT workspaces

The default workspace of Corel PHOTO-PAINT is designed to provide a more intuitive placement of tools and controls. The default settings are included in `PHOTO-PAINTUI.xml`, which is located in the `CorelDRAW Technical Suite\27\PHOTO-PAINT\UIConfig` folder. In addition, the following workspaces for Corel PHOTO-PAINT are installed in the `CorelDRAW Graphics Suite\27\PHOTO-PAINT\Workspace` folder:

- `lite.cdws` — ideal for new users who are getting started
- `photoshop.cdws` — designed for Adobe Photoshop users
- `Default(TM).cdws` — has a streamlined user interface (UI) that displays only the tools and commands that users are most likely to use when using a tablet

Custom workspaces

You can customize all available workspaces by modifying the CDWS (CorelDRAW Workspace) files. You can also create a custom workspace from within Corel DESIGNER, CorelDRAW or Corel PHOTO-PAINT, and you can customize the default workspace.

With CorelDRAW Technical Suite you can deploy customized workspaces and any new workspaces you create with the installation. You can also deploy custom default workspaces.

To deploy custom workspaces with the installation

- 1 Create the server image. For more information, see [“Stage 2: Creating the server image” on page 9](#).
- 2 Create the custom workspaces you want to add to the server image.

To create a custom workspace, you must start Corel DESIGNER, CorelDRAW or Corel PHOTO-PAINT as a local user. For information about how to create and export workspaces, see the Help topic “Create workspaces” (Help ► Product Help).

- 3 Install **CorelDRAW Technical Suite** on a workstation, and log in as a local user.
- 4 Copy the custom workspace files to the corresponding **Workspace** folders in the server image, making sure not to delete any existing workspace files.
msis\Program files 64\Corel\CorelDRAW Technical Suite\27\Designer\Workspace
MSIs\Program files 64\Corel\CorelDRAW Technical Suite\27\Draw\Workspace
MSIs\Program files 64\Corel\CorelDRAW Technical Suite\27\PHOTO-PAINT\Workspace
- 5 Deploy the server image. For more information, see “Stage 3: Installing the software” on page 15.
Users can access the custom workspaces after they start the applications.

To deploy custom default workspaces with the installation

The default workspace files of Corel DESIGNER, CorelDRAW and Corel PHOTO-PAINT `_default.cdws` are created when the applications are launched for the first time. You can customize the default workspaces, and then you can deploy them similarly to the way you can deploy other custom workspaces.

- 1 Install CorelDRAW Technical Suite on a workstation, and log in as a local user.
- 2 Start Corel DESIGNER, CorelDRAW or Corel PHOTO-PAINT, and customize the workspace.
- 3 Copy the `_default.cdws` file from the respective user folder.
C:\Users\[User Name]\AppData\Roaming\Corel\CorelDRAW Technical Suite 2026\Designer\Workspace
C:\Users\[User Name]\AppData\Roaming\Corel\CorelDRAW Technical Suite 2026\Draw\Workspace
C:\Users\[User Name]\AppData\Roaming\Corel\CorelDRAW Technical Suite 2026\PHOTO-PAINT\Workspace
- 4 Follow steps 3 and 4 from “To deploy custom default workspaces with the installation” on page 34.



If you want to add custom workspaces after the software has been deployed, you must repair each workstation installation using the following command line:

```
<AdminImagePath>\Setup.exe REINSTALL=ALL REINSTALLMODE=oums /qn
```



To access the new custom workspaces, users must restart the applications while holding down **F8**.

Working with MSI files

Stored in the Setup folder, the main Microsoft Windows Installer (MSI) file for the setup — `\x64\msis\Setup_x64.msi` — contains a database of main features, registry keys, folders, and shortcuts for the software.

The server image contains a copy of the main setup MSI file — the MSI tables within which you can modify for deployment to the workstations.

Various components of the software are stored in additional MSI files. Some of these MSI files are required by the setup, while others represent optional features of the software.

Setup files

Besides `Setup_x64.msi`, the setup requires an addition MSI file to carry out the installation: `x64\ICA_x64.msi`.

Language modules

The setup requires at least one language module, MSI files for which are stored at `x64\msis` (64-bit) on the installation disc. XVL Studio Corel Edition and XVL Studio 3D CAD Corel Edition support only German (DE), English (EN), French (FR) and Japanese (JP). However, some versions of CorelDRAW Technical Suite may include additional language modules for the remaining components (CorelDRAW and Corel PHOTO-

PAINT). The following table lists all language modules that the software may contain. The language modules that are available vary with each edition of the software.

Language module	MSI file
Brazilian Portuguese	BR_x64.msi
Chinese (Simplified)	CS_x64.msi
Chinese (Traditional)	CT_x64.msi
Czech	CZ_x64.msi
Dutch	NL_x64.msi
English	EN_x64.msi
French	FR_x64.msi
German	DE_x64.msi
Italian	IT_x64.msi
Japanese	JP_x64.msi
Polish	PL_x64.msi
Russian	RU_x64.msi
Spanish	ES_x64.msi
Swedish	SV_x64.msi
Turkish	TR_x64.msi

Programs

To install the programs included with the software, the setup uses the following MSI files at X:\x64\MSIs on the installation disc.

Program	MSI file
CAPTURE	Capture_x64.msi
Corel DESIGNER	Designer_x64.msi

Program	MSI file
Corel Font Manager	FontManager_x64.msi
CorelDRAW	Draw_x64.msi
Corel PHOTO-PAINT	PHOTO-PAINT_x64.msi

Features

To install the various components of the software, the setup uses additional MSI files stored at `Setup\x64\msis` on the software ISO file or in the `\MSIs` folder of the server image. These files include the following.

Feature	MSI file
Ghostscript general public license, for EPS and PostScript import	Ghostscript_v10.msi
Microsoft Visual Basic for Applications (VBA)	\msis\vba\vba71.msi
Microsoft Visual Studio Tools for Applications (VSTA)	\msis\vsta\vsta_setup.exe
Windows Shell Extension	ShellExt.msi



You can exclude optional MSI files from the setup by creating a customized server image. Excluding an MSI file prevents the corresponding feature from being installed.

Working with registry keys

After creating the server image, you may want to edit its registry keys for deployment to the workstations. By doing so, you can avoid having to manually configure the registry keys of each individual workstation installation of the software.

Setting up dynamic language switching

Dynamic language switching allows the language of the user interface to be changed, both during and after installation. This feature requires the installation of multiple language modules for the software — one for each desired user-interface language (see [“Specifying UI modules by language code” on page 31](#)). The selection of languages you can implement depends on the license you have purchased.

Two sets of registry settings are required for dynamic language switching:

- workstation settings
- current user settings

Workstation settings

Workstation settings affect all users. The registry setting for each workstation is as follows:

```
HKEY_LOCAL_MACHINE\SOFTWARE\Corel\Corel DESIGNER\27.0\Languages
```

Inside this key are language keys — three-letter codes that represent the available languages. These language keys are put in place by the setup, so no intervention is required. Shown here (for reference only) are the three-letter codes for the available languages for the remaining components.

Language	Code
Brazilian Portuguese	PTB
Chinese (Simplified)	CHS
Chinese (Traditional)	CHT
Czech	CSY
Dutch	NLD
English	ENU
French	FRA
German	DEU
Italian	ITA
Japanese	JPN
Polish	PLK
Russian	RUS
Spanish	ESN
Swedish	SVE
Turkish	TRK

Under each language key are the following registry settings:

- **DirName** — specifies the name of the folder for the language-specific files, relative to *InstallationPath*\Languages
- **UIName** — specifies the name to show in the startup dialog box and on the **Tools ▶ Options ▶ Global** dialog box (**General** page)

Current user settings

The registry setting for each current user is as follows:

`HKEY_CURRENT_USER\Software\Corel\Corel DESIGNER\27.0`

The **UILang** setting is not initialized by the setup because the setup cannot determine which user will run the applications. After the user has run the application once, this setting changes to the three-letter code that corresponds to the user-specified language key at the following location:

`HKEY_LOCAL_MACHINE\SOFTWARE\Corel DESIGNER\27.0\Languages`

Configuring content for offline availability

Note that Corel Content Exchange — the online storage for content accessible from earlier versions of the suite — is no longer available. Users can download content packs from the **Get More** page of the Welcome screen when working in online mode. However, we recommend that you make the content available to them on a network drive to facilitate their work.

The Proof of Entitlement Certificate email will contain a URL linking to a shared drive containing the extra content, which you can download. After you unzip the extra content to the location you want, you can create aliases to the various content folders from within Corel DESIGNER or CorelDRAW. When you create aliases, a database file is created. To make it easier for users to find and search the extra content, you must deploy this database file to the workstations.



The extracted content is 5.75 GB.

Internet access is required to access the download location.

To unzip the content

- 1 On the server that you are going to make available to all workstations, create a main content folder and name it **Corel Content**.
- 2 Follow the content URL provided on your Proof of Entitlement Certificate email. There are five main archive files: Applications, Fills, Fonts, Images, and Templates. The **Images** folder includes clipart and photos that are organized by theme in separate folders.
- 3 Extract the archive files into separate folders using a decompression tool to the folder created in step 1.



When all zip files have been downloaded and decompressed, you should see the following folders:

- Applications
- Fills
- Fonts
- Images
- Templates

Once the content is available on the server, users can create aliases to the folders so that they can access the content from within the **Assets** docker (formerly known as CONNECT Content docker), the **Fill** and **Transparency** pickers, and the **New from Template** dialog box in Corel DESIGNER or CorelDRAW. However, we recommend that you create the aliases yourself so that it is easier for users to access extra content.

To create aliases to the subfolders in the Images folder

- 1 Do any of the following:
 - In Corel DESIGNER, click **Window** ► **Assets**.
 - In CorelDRAW, click **Window** ► **Dockers** ► **Assets**.
- 2 In the **Assets** docker, click the **Local and network assets** button below the **Search** box.
- 3 Open the **Choose content source** list box, and click **Add new**.
- 4 Click **Create alias**.
- 5 In the **Locate content library** dialog box, browse to a subfolder in the **Images** folder located on the server.
- 6 Click **Select Folder**.
Repeat steps 3 to 5 to create aliases to other subfolders in the **Images** folder.



You can create an alias to the Images folder as well. Note, however, that it takes a long time to generate the thumbnails of all images. That's why we recommend that you create aliases to the subfolders.

To create an alias to the Fills folder

- 1 In Corel DESIGNER or CorelDRAW, open the **Fill** picker or the **Transparency** picker in the **Fill** or **Transparency** section of the **Properties** docker (Corel DESIGNER: **Window** ► **Properties**; CorelDRAW: **Window** ► **Dockers** ► **Properties**).
 - 2 In the **Locate fills library** dialog box, open the **Choose content source** list box, and click **Add new**.
 - 3 Click **Create alias**.
 - 4 In the **Locate fills library** dialog box, browse to the **Fills** folder located on the server.
 - 5 Click **Select folder**.
- Repeat steps 2 to 5 to create aliases to the subfolders in the **Fills** folder.

To create an alias to the Templates folder

- 1 In Corel DESIGNER or CorelDRAW, click **File** ► **New from Template**.
 - 2 In the **New from Template** dialog box, open the **Choose content source** list box, and click **Add new**.
 - 3 Click **Create alias**.
 - 4 In the **Locate template library** dialog box, browse to **Templates** folder, located on the server.
 - 5 Click **Select folder**.
- Repeat steps 2 to 5 to create aliases to the subfolders in the **Templates** folder.



To share content (fills, templates, and images) created by your company with the workstations, you can use the same method of creating aliases to network folders from within Corel DESIGNER or CorelDRAW.

Deploy the content database file

When you create aliases, a simple database file is generated. This file is called `UserCollections.db` and resides in the following location:

- `AppData\Roaming\Corel\Databases\Assets V1.3`

After you deploy the content database file to the workstations, users will be able to search and use content from the alias folders.

Customizing the setup fileset

The main configuration file `Setup.xml`, located in the `x64` folder, lists all features included in the setup.

When you create a server image, a copy of the `Setup.xml` file is included. If you want to customize the setup fileset on the server image, you must edit the `Setup.xml` file to reflect your desired changes.

Understanding Setup.xml

The `Setup.xml` file contains four main types of nodes. With an understanding of these four nodes, you can modify the `Setup.xml` file to create a customized server image.

<Msi/> nodes

Each `<Msi/>` node specifies a main setup file, such as an executable (EXE) file, a self-extracting ZIP file, or an MSI file that bundles (or "chains") other MSI files.

For example, you can exclude Ghostscript from the installation by making the following modification.

```
<!--Msi productcode="Ghostscript"  
file="msis\Ghostscript_v10.msi" cmdline="ALLUSERS=1  
ADDLOCAL=ALL" adminsupport="0" condition="GPL=1" progresstext="Str.ProgressText.Common" /-->
```

<Dbm/> nodes

Each **<Dbm/>** node specifies a component of a **<Msi/>** node — typically, an MSI file. A **<Dbm/>** node has the following structure, where *GUID* is the associated product code, and *MSI* is the path and filename of the MSI file:

```
<Dbm productcode="{GUID}" file="MSI" />
```



Some **<Dbm/>** nodes also require a condition.

If you want to apply an MST file to the specified MSI file, you can use the following syntax (in cases where the MST and MSI files are in the same folder, *MST* is the filename of the MST file; in cases where the MST and MSI files are in separate folders, *MST* is the path and filename of the MST file):

```
<Dbm productcode="{GUID}" file="MSI"  
cmdline="TRANSFORMS=MST"  
progresstext="Str.ProgressText.name" />
```

<Feature/> nodes

Each **<Feature/>** node specifies a feature that is associated with an MSI file. A **<Feature/>** node has the following format, where **name** is the name of the MSI file and **feature** is the name of the associated feature:

```
<Feature name="Str.Feature.name"  
desc="Str.Feature.name.Desc" property="feature">
```



Some **<Feature/>** nodes have subnodes.

For a list of the available features, see [“Deploying a custom set of features”](#) on page 29.

<Property/> nodes

Each **<Property/>** node specifies a property. A **<Property/>** node has the following structure, where *property* is the name of the public property and **value** is its value:

```
<Property name="property" value="value" />
```



For a list of available public properties, see [“Using public properties”](#) on page 19.

Creating a server image with a customized fileset

You can use **Setup.xml** to create a server image with a customized fileset.

To create a server image with a customized fileset

- 1 Copy the server image to a new location.
- 2 Add any desired language-module MSI files to the server image.
- 3 Edit **Setup.xml** to reflect the additions you’ve made to the fileset:
 - Add an **<Msi/>** node for each new setup file.

- Add a **<Dbm/>** node for each new language-module MSI file.
- Add the following **<Property/>** node for each new language-module MSI file, where \$\$ is the language:

```
<Property name="Include.$$" value="1" />
```

4 Edit **Setup.xml** to reflect the removals you've made from the fileset:

- Remove the corresponding **<Msi/>** node for each removed setup file.
- Remove the corresponding **<Dbm/>** node for each removed MSI file.
- Remove the corresponding **<Feature/>** node and subnode for each removed MSI file.
- Adjust any corresponding **<Property/>** nodes by changing their value.

For example, let's say that you're creating a single-language setup from a multi-language setup. To record the fileset changes in the **Setup.xml** file, you must remove the corresponding **<Dbm/>** and **<Feature/>** nodes for each removed language module. Next, you must set each **<Property/>** node for **Include.\$\$** to a value of **0**, where \$\$ is a removed language module. The **<Property/>** node for **ShowApplicationLanguageSelector** is automatically set to a value of **0**.

Deploying customized installation settings

To modify the settings used to install the software on the workstations, you can use the **Persist.xml** file stored at the root of the server image.

Each entry in **Persist.xml** corresponds to a public property for the software (see "Using public properties" on page 19). The syntax of each entry is as follows:

```
<Property name="property" value="value" />
```

By modifying the value of an existing entry in **Persist.xml** — or by adding a new entry — you can customize the installation settings deployed from that server image. This deployment method offers an excellent alternative to creating a different server image or customizing a command line.

You must modify **Persist.xml** before installing the software on the workstations for the changes to take effect.

Example 1

You can use the following **Persist.xml** entry to specify that automatic software updates are enabled:

```
<Property name="ALLOW_PRODUCTUPDATES" value="1" />
```

By changing the value of this entry from **"1"** to **"2"** (and saving this change to **Persist.xml**), you can disable automatic updates for the workstation installations.

By changing the value of this entry from **"1"** to **"0"** (and saving this change to **Persist.xml**), you can check for updates and let the user choose when to install the update.

Example 2

You can use the following **Persist.xml** entry to specify the ProfileID and add account credentials to the server image:

```
<Property name="PROFILEID" value="XXXXXXXX" />
```

Specifying a value for the ProfileID will ensure that all workstations are automatically signed in to the account after installation. For information about accessing the ProfileID, see "ProfileID" on page 11.

Example 3

You can use the following **Persist.xml** entry to allow users to take advantage of Welcome screen features:

```
<Property name="WELCOMESCREENONLINE" value="on" />
```

Note that the Welcome screen cannot be used without enabled internet features.

Example 4

You can use the following **Persist.xml** entry to specify the serial number for the installation:

```
<Property name="SERIALNUMBER" value="SN" />
```

By changing the "SN" value, you can specify a different serial number for the workstation installations.

For more information, see ["SERIALNUMBER" on page 21](#).

CorelDRAW[®]

TECHNICAL SUITE 2026



Appendix B: Authenticating the software

If you signed in by providing corel.com account credentials when creating the server image, all users are automatically signed in and have access to internet-based features.

Note that access to updates and internet-based features requires software authentication of the workstations. In this appendix, you will learn about what information is exchanged during software authentication and what is required for successful authentication.

In this appendix

- “Exchanging information during authentication” (page 43)
- “Requirements for authentication” (page 43)

Exchanging information during authentication

The first time a CorelDRAW Technical Suite application is launched on a workstation, on any given day; the following information is sent to the Corel server that authenticates the software:

- Information that identifies the corel.com account, which can be either the email address and password or the ProfileID. For information about accessing the ProfileID, see “ProfileID” on page 11.
- Information that identifies the workstation on which the application is launched such as computer and hardware signature and name.
- Product identifiers that specify the product family (such as CDGS for CorelDRAW Graphics Suite or CDTS for CorelDRAW Technical Suite), product version, language as well as the product serial number.
- Information about the license state.

The Corel server returns feature identifiers that enable online features such as QR codes.

Requirements for authentication

For successful software authentication on a corporate network, allow access to <https://iws.corel.com>, the address of the Corel authentication server. Use port 443, with the following endpoint: <https://iws.corel.com>. If the sign-in dialog appears, ensure access to <https://ipm.corel.com>, <https://idp.coreldraw.com>, <https://wll741ba4c.execute-api.us-east-1.amazonaws.com/prod/getautheninfo>, and <https://myaccount.corel.com> for authentication.

To allow access to the Corel authentication server, you may need to modify the security settings in your proxy or firewall software.

CorelDRAW[®]

TECHNICAL SUITE 2026



Appendix C: FAQ

This section includes answers to frequently asked questions.

Why do I need a corel.com account?

A corel.com account is required to create the server image with online access and authenticate the product. For more information, see [“corel.com account” on page 9](#).

My corel.com account credentials no longer work.

Make sure to use the corel.com account associated with the product. You must type in the credentials used when you first ran the administration installation.

Why do I need to authenticate the product?

To give users access to updates and internet-based features, you can authenticate the software when you create the server image by signing in with your corel.com account credentials. Authentication also takes place on the workstations but it is a silent process that doesn't require user sign-in. You also have the option of inviting users to authenticate their license with their personal corel.com account credentials at the first application launch after installation. For information about what information is exchanged during software authentication, see [“Appendix B: Authenticating the software” on page 43](#).

Can I give users access only to some internet features?

You cannot enable or disable individual internet-based features. For example, you cannot allow users to download content packs from the Welcome screen, but prevent them from accessing online videos or using the QR feature.

How can I give users access to Corel content?

Extra content can be downloaded from the **Get More** dialog box, accessible from the Welcome screen when users work in online mode.

In addition, the Proof of Entitlement Certificate email includes a link to the Corel content provided with the software. You must copy the content to a network drive and give users access to this drive. In addition, you need to create aliases to the content folders to make content such as fills and transparencies accessible from within the software. For more information, see [“Configuring content for offline availability” on page 38](#).

Can users on the workstations and I use the software in offline mode?

Yes, it is possible if you have a license with a long serial number (37 characters) and use this serial number to create a server image. For more information, see [“Setting up the server image” on page 10](#).

Where can I manage my installations?

You can manage your installations from the corel.com account that was used to sign in and create the server image. For example, you can remove specific workstations from Your Account page.

I deployed the software using a server image, yet the workstations are still asked to sign in. Why?

The sign-in may be required for one of the following reasons:

- You signed in with your corel.com account credentials when you created the server image to deploy the software in online mode. However, the workstation was not online when the user first launched the product. In this case, the workstation attempts to access iws.corel.com, the Corel authentication server, to authenticate the software.
- You invited users to authenticate their license with their personal corel.com account credentials, which requires signing in at the first application launch after installation.
- You have removed the workstation from Your Account page of your corel.com account. When a workstation is removed, it cannot be signed-in automatically. The user of the workstation must sign in once.
- If the workstation is offline for a long time after the sign-in, software authentication is required to make sure that product entitlements have not changed or expired.